

Инструкция по настройке APN

Данная инструкция применяется для настройки APN в подавляющем большинстве терминалов.

1. Настройка терминалов «CDMA/VoLTE» и «Only VoLTE»:

- Выполнить сброс настроек APN;
- Создать APN «IDC LTE»;
- Создать APN «IDC IMS»;
- Создать APN «IDC CDMA» (для CDMA/VoLTE);
- Сделать APN «IDC LTE» активным.

2. Настройка терминалов «CDMA/LTE»:

- Выполнить сброс настроек APN;
- Создать APN «IDC LTE»;
- Создать APN «IDC CDMA»;
- Сделать APN «IDC LTE» активным.

3. Настройка терминалов «Only CDMA»:

- Выполнить сброс настроек APN;
- Создать APN «IDC CDMA»;
- Сделать APN «IDC CDMA» активным.

Список APN и их параметров:

APN «IDC LTE»	APN «IDC IMS»	APN «IDC CDMA»
carrier(имя)="IDC LTE" apn="4g.idknet.com" mcc="259" mnc="15" type="default,mms,supl,internet" mmsc="http://mmsc.idknet.com/servlets/mms" mmsport="9201" mmsproxy="217.19.208.21" protocol="IPV4V6" user="idc" password="idc" authtype="PAP CHAP"	carrier(имя)="IDC IMS" apn="ims" mcc="259" mnc="15" type="ims" protocol="IPV4V6"	carrier(имя)="IDC CDMA" apn="idc" mcc="255" mnc="00" type="default,mms,supl,internet" protocol="IP" или "IPV4" user="idc" password="idc" mmsc="http://mmsc.idknet.com/servlets/mms" mmsport="9201" mmsproxy="217.19.208.21" roaming_protocol="IP" или "IPV4" authtype="PAP CHAP"